Subject: [SSGM Plugin] EvacPlugin

Posted by Neijwiert on Tue, 10 Oct 2017 23:11:14 GMT

View Forum Message <> Reply to Message

This plugin is used to evacuate n amount of soldiers (they will be destroyed once they are evacuated)

It contains the following scripts:

- GK Evac Monitor

Script parameters:

- NotifyObjId: The ID of an object which receives some customs to react upon what is happening with the evac

GK_CUSTOM_EVENT_EVAC_FAILED: when the evac failed. The param specifies the reason Param:

GK_EVAC_FAILED_REASON_CANCELED: when the evac is canceled via custom

GK_EVAC_FAILED_REASON_PERSON_FAILED_TO_MOVE_TO_EVAC_LOCATION: when an evac person failed to move to the evac location

GK EVAC FAILED REASON CHOPPER KILLED: when the evac chopper is killed

GK_EVAC_FAILED_REASON_TOO_MANY_EVAC_PERSON_DEATHS: when too many evac persons died

GK_CUSTOM_EVENT_EVAC_PERSON_KILLED: when an evac person is killed. The param is the person's id.

GK_CUSTOM_EVENT_EVAC_PERSON_FAILED_TO_MOVE_TO_EVAC_LOCATION: when an evac person failed to move to the evac location. The param is the person's id.

GK_CUSTOM_EVENT_EVAC_PERSON_EVACUATED: when an evac person is evacuated. The param is the person's id.

- MaxEvacPersonDeaths: the maximum of evac persons that can die before it is considered failed
 - TransportPreset: the preset name for the evac chopper
 - CanChopperBeSeen: If objects with Enable_Enemy_Seen can see the chopper
 - CanChopperBeDamaged: Can the chopper be damaged at all
- GK Evac_Person

Script parameters:

MonitorObjId: The id of the monitor object (GK_Evac_Monitor)

Below scripts are also included, but they are used internally and don't need to be manually attached. I will not explain their script parameters.

GK Evac Anim Cinematic

GK_Evac_Chopper_Cinematic_Item

GK Evac Generic Cinematic Item

GK Evac Troop Bone

Example:

GameObject *evacMonitor = Commands->Create_Object("Invisible_Object", Vector3()); int evacMonitorId = Commands->Get_ID(evacMonitor); Commands->Attach Script(evacMonitor, "GK Evac Monitor", "0, 1,

GDI_Transport_Helicopter_Flyover, 1, 0");

GameObject *evacPerson1 = Commands->Create_Object("GDI_MiniGunner_0", Vector3()) Commands->Attach_Script(evacPerson1, "GK_Evac_Person", StringClass::getFormattedString("%d", evacMonitorId));

GameObject *evacPerson2 = Commands->Create_Object("GDI_MiniGunner_0", Vector3()) Commands->Attach_Script(evacPerson2, "GK_Evac_Person", StringClass::getFormattedString("%d", evacMonitorId));

Then all you need to do is send a custom to the evac monitor GK_CUSTOM_EVENT_EVAC_INITIATE_EVAC

I based this on the logic of the evacuations in M01 and I improved it. The scripts should be singleplayer compatible. (Save/Loading working). You also have the ability to cancel an ongoing evacuation with the custom GK_CUSTOM_EVENT_EVAC_CANCEL_EVAC.

SOURCE CODE: https://github.com/Neijwiert/C-C-Renegade-EvacPlugin

EDIT: Oh the evac will take place at the location of the monitor.

UPDATE:

Fixed issue where an evac person could be killed/destroyed during evac and then the evac would not continue

Fixed an issue where the troop bone and evac person could get out of sync and the troop bone would finish before the evac person. This would cause a freeze in the evac sequence.

Also a nice video: https://youtu.be/Nifmw1LRoJI

Ignore the soldiers sometimes doing weird animations when being evaced, that's just the Renegade engine. I first evacuate alot of people and the second time I'm canceling the evacuation

File Attachments

1) EvacPlugin.dll, downloaded 266 times